

Photoshop CS Ato Z

The essential visual reference guide

江苏工业学院图书馆 一藏 书 章





Words and design: Peter Bargh
Produced using Adobe's InDesign DTP program – it's awesome!
All photographs: Peter Bargh
e-mail peter@bargh.co.uk

Focal Press
An imprint of Elsevier
Linacre House, Jordan Hill, Oxford OX2 8DP
200 Wheeler Road, Burlington MA 01803

First published 2004

Copyright © 2004, Peter Bargh. All rights reserved

The right of Peter Bargh to be identified as the author of this work has been asserted in accordance with the Copyright, Designs and Patents Act 1988

No part of this publication may be reproduced in any material form (including photocopying or storing in any medium by electronic means and whether or not transiently or incidentally to some other use of this publication) without the written permission of the copyright holder except in accordance with the provisions of the Copyright, Designs and Patents Act 1988 or under the terms of a licence issued by the Copyright Licensing Agency Ltd, 90 Tottenham Court Road, London, England W1T 4LP. Applications for the copyright holder's written permission to reproduce any part of this publication should be addressed to the publisher.

Permissions may be sought directly from Elsevier's Science and Technology Rights Department in Oxford, UK: phone: (+44) (0) 1865 843830; fax: (+44) (0)1865 853333; e-mail: permissions@elsevier.co.uk. You may also complete your request on-line via the Elsevier homepage (www.elsevier.com), by selecting 'Customer Support' and then Obtaining Permissions'

British Library Cataloguing in Publication Data

A catalogue record for this book is available from the British Library

Library of Congress Cataloguing in Publication Data

A catalogue record for this book is available from the Library of Congress

ISBN 0 240 51957 4

For information on all Focal Press publications visit our website at: www.focalpress.com

Thanks to:

Will Smith and Tracey Johnson for their invaluable assistance on ePHOTOzine.

All the musicians in the world who provide me with great sounds.

This week I have mostly been hearing Bjork, Sigur Ros and Tricky.

And a special thank you to everyone who made

Photoshop 5.5, 6.0 and 7.0 A to Z a huge success.

Words of the day: Kumquat, Aardvark, Plop, Whatever Saying of the day: Candle in the eye

Printed and bound in Italy




















Introduction

Photoshop is, arguably, the most complex image editing program sold, but it's equally the most versatile when you become familiar with its tools and functions. Many of the reference books written about Photoshop are as complex as the program, but they don't have to be. Photoshop CS A to Z has been produced to present the program in a visual way and in a logical order.

It's too easy to get lost wading your way around a 300 page book trying to find out how a certain feature works. In this book you look up the mode, tool or filter, presented in a logical A to Z order, to find a visual reference with handy tips and quick keys.

The book can be used as a helpful guide to keep near your computer, giving you nuggets of essential information as you work. It will also give you plenty of ideas to try out on your own pictures.

It's really important when working with a program like Photoshop that you set it up to work better for you. To do this there are a selection of preferences that are used to take the program off the original settings and customize it to your liking. I've included an explanation of all these in the appendices, along with an area where you can make notes of filter settings that work well so you can refer back to them when using the filters again.

Because of the logical steps Adobe have made with their upgrades, this book is also suitable for owners of earlier versions of the program; there's a comparison of all the versions of Photoshop, including LE, and the budget program from Photoshop called Elements in Appendix A. Those wondering what happened to version numbers, this is really version 8.0, but Adobe have decided to replace the version number with CS, which stands for Creative Suite, and forms part of a new family of Creative Suite programs.

As an English author I would naturally prefer to use English spellings, for example colour instead of color, but as the book will be sold throughout the world I've adopted the US spelling for the word color. This ensures the book is consistent with the Photoshop users' manual and interface.

In the first three books I used Apple Mac screengrabs throughout, simply because I'd used a Mac for years in favour of the PC. I've recently switched to PC so many of the screengrabs are now from the Windows XP platform. Essentially Photoshop runs the same whichever platform you work on. The main difference is when a keyboard shortcut includes the Command key on a Mac you would use the Ctrl key on a PC. Similarly when the Option key is used on a Mac the Alt key should be used on the PC, and the Return key on the Mac is Enter on the PC. You'll also see subtle differences in the look of palettes on a Mac over a PC, but all the options are in the same place. Enjoy!


Peter Bargh, 2004

Rete Borgh

Contents

A Actions to Automate	1	Magic Eraser to Multi-page PDF to PSD	103
B Background color to Button mode	11	N Navigator palette to Note	109
C Calculations to Custom Shape tool	27	Opacity to Output levels	113
D Define Brush to Duplicating layers	45	P Page Setup to Purge command	115
E Edges to Eyedropper	55	Q Quadtones to Quick Mask mode	129
F Fade command to Fuzziness setting	61	R RAM to Rotate Canvas	131
G Gamut warning to Guides	71	S Saturation to Stylize filter	133
H Healing brush to Hue	79	T Texture filters to Type tool	145
Image Assistant to Inverting	85	U Undo to Unsharp Mask	153
J JPEG to Joiner	89	Variations to Version Cue	155
K Keyboard shortcuts to Kodak Picture CD	91	W Watermarks to Workspace	156
L Lab Color to LZW compression	93	Z Zoom tool to ZoomView	158

Index		159
Appendix A	Photoshop versions compared	161
Appendix B	Typefaces	163
Appendix C	Useful shortcuts	165
Appendix D	Preferences	167
Appendix E	Useful Web sites	171
Appendix F	Plug-in filters	175
Appendix G	Recording sheets	181



abcdefahijklmnoparstuvwxyz

Actions Active layer Adjustment layer **Airbrush Align Linked** Alpha channels **Anchor points Anti-aliasing** Apply image **Art History Brush Artifacts Artistic filters** Assign profile **Audio Annotation tool Auto Color correction Auto Contrast Auto Levels Automate**

Actions

MENU

WINDOW →

OUICK KEY F9

An action is a way of automatically applying a technique to an image using a prerecorded series of commands, or a script.



You can turn part of an action on or off, as well as record, play or edit new or existing actions.

that is triggered by pressing one or a combination of keys. Many actions are already supplied with Photoshop and can be found at the bottom of the Actions menu by clicking on the arrow at the top right of the Actions palette. They can also be found



in the Presets folder.
An action can be as simple as opening a new canvas or as advanced as creating a drop shadow on an existing picture or, as in our example (left), making snow.

You can also create your own Photoshop actions using the Automate mode, so if there are techniques you find particularly fiddly or ones you'll want to use again, record the commands as you run through them and assign the action a shortcut key.

To record a new action open an image and select New Action

from the hidden menu or click on the page icon at the bottom of the palette. This displays



a new palette. Name your action, choose a destination folder, a shortcut key and a color for the button display.

The shortcut can be a single F button or any combination of an F along with Shift and Control keys. Click on the record button and run through the various steps to produce the desired result. You'll see each step appear in the menu as it's recorded. When you've done click stop.


Now when you want to apply the recorded effect just click on the designated shortcut key. Actions can also be applied to several images in one go using the Batch command or created into droplets. (See Batch command and Droplets)

- If a command cannot be recorded you can insert it manually using the Insert

 Menu command
- If you make a mistake, keep going, you can edit the script later.
- Some settings may need modifying for different images. Clicking on the box to the left of the action will stop the script at that point and bring up the dialogue box so you can manually adjust before continuing the script.

Active layer

This is the layer that is currently selected. To select a layer click on the layer icon in the layers palette. The layer will become highlighted and when a filter effect or brush is applied it will only affect the highlighted layer.





Airbrush

A painting tool that applies a color in much the same way as a real airbrush. The airbrush moved from the toolbar in Photoshop 7.0 and appears in the brush options bar. Now you simply choose airbrush as a style and select how you want it to work from the brush palette.



Hold down the mouse and drag it around to spray color evenly onto the canvas. Hold it in the same place and color builds up while spreading outwards. Covering an area that's already sprayed increases color depth.

As with all brush modes you can specify size, blending mode and opacity from the bar that appears at the top of the page when you click on a brush. There's also an option to adjust flow.

The

- Select a start point, hold down the Shift key and click an end point to paint a straight line.
- Use the Airbrush on low pressure with black paint to create shadows.
- Switch on Caps lock to turn the Airbrush standard cursor into a precision crosshair.

Adjustment layer

MENU LAYER →
NEW ADJUSTMENT LAYER


An adjustment layer is a layer that you can apply effects to that will change all the layers below it in the stack. If you then turn off the eye icon next to the layer it will turn off the effects for that particular adjustment layer. It's great for hand coloring black & white pictures as well as controlling levels or curves.



You can delete these layers at any time to remove the effect.



A Hue/Saturation Adjustment layer was used to color this infrared black & white original. Make a selection of an area and save it as an Adjustment laver. You can then adjust the color of just that selection without affecting the rest of the picture, as illustrated here. At this stage I was trying out a violet colored temple.





Tin

In Version 5.5 open from Layer→New→Adjustment Layer.

a

Align Linked

MENU LAYER →
ALIGN LINKED

Feature introduced in Photoshop CS to

make it easier to align items within layers. Select this option and one of the six align options to make objects on linked layers align to the top, centre or bottom edge in either horizontal or vertical directions.



Here Align to left edges has been selected and the three images have lined up to the left while maintaining their horizontal positions.



Anchor points

QUICK KEY J SELECTS IT FROM TOOLBOX The small square boxes that are

placed around an object when you make a selection with the Pen tool. The points can be moved when they've been placed using the Direct Selection tool.



Apply image

MENU IMAGE → Used to blend one image layer and channel with another. The source and destination image have to be the same size. I found the effect works well using the same image with the blend option. It's very much a trial and error process but well worth the effort as seen here as I've appeared to change the time of day

in one simple step. (See Calculations)

Alpha channels

These are ideal for saving selections separate from the RGB or CMYK channels. Carefully draw round a subject and choose Select→Save Selection once you're happy with the selection. This is stored at the base of the Channels palette as a separate

channel - the Alpha channel.

It can be recalled and the selection applied to the image at any time by calling up Load Selection from the Select menu. This saves you having to reselect a subject later. Up to 53 Alpha channels can now be added to an RGB image allowing you to produce very complex selections that can be recalled to make changes to a variety of detailed parts of the image at any time.






Anti-aliasing

Aliasing occurs when the sharp edges of pixels appear jagged on the straight edges of an image or text.

Photoshop uses anti-aliasing to smooth out the edges by making the pixels semi-transparent so that they pick up color from surrounding pixels. It's useful when cutting or copying and pasting selections onto new backgrounds. Anti-aliasing can make the image look a little blurred when viewed close up.



Pixels make round edges look jagged. Using anti-aliasing smooths the 'jaggies' by adding midtone pixels to the harsh edge. Here two circular selections have been made – one with anti-aliasing on (bottom) and one with it off (top). Then the selections were copied and pasted onto a white background. Notice how sharp the top cutout looks.



Moonlit scene, made possible by the Subtrac Blend mode and green channel



the bigger the paint daubs and less realistic the effect.

Colorful images like this are suitable for the Art History Brush attack.





Setting Fidelity to a low value produces brush strokes that have more color than the source point (left). A high value maintains the source color (right).



Using one of the other custom brushes from Photoshop's Presets folder will produce more unusual results. Here two of the

Special effect brushes were used with Fade mode to create an oil paint style photograph.





To lerance: 0%



Area: 50 px

With a small brush and careful choice of the palette options paint effects can be quite realistic (above).

Choose too large a brush size and the effect could go completely wrong (left). You could use this sort of treatment as background to text, though.



You can also use the technique to paint around the head of a bride to create a pretty vignette/diffuser style effect.

a

Artifacts

Digital photography, like any form of image capture, can produce faults. In digital photography they're referred to as artifacts and can be caused by a number of problems including flare from the camera's lens, electrical interference or low resolution CCDs. Low resolution CCDs cause curved edges to appear jagged as the curve takes on the square edges of each pixel – known as Aliasing.

Blooming is less of a problem now but occurred on earlier CCDs when the electrical charge exceeded the pixel's storage capacity and crossed into adjacent pixels causing image distortion. We've all seen the TV presenter with the stripy shirt appearing as a strange colored pattern. The same thing happens on CCDs and it's known as color fringing.





This photo from a digital camera's economy mode, shows the high level of compression has caused the unusual artifacts in certain areas.

Artistic filters

MENU FILTER →
ARTISTIC

Change your picture into a

painterly image using this collection of filters that mimic natural or traditional artists' effects. Each filter has a selection of sliders which I'll explain for the Colored Pencil (below).

For the rest I've used the same image and included settings I made, but you should experiment with your photos, because each filter suits different images.

Also try using the Edit→Fade option with a Blend mode. (See Fade)



COLORED PENCIL

Produces a rough crosshatch effect by drawing in a pencil style over the original using the background color. Edges are retained and the original background image shows through the pencil strokes. Moving the pencil width slider to the left makes the pencil lines thin while sliding to the right makes them thick.

Stroke pressure controls the accuracy of the lines over the original image. Moving over to the left fills the image with color and to the right produces deep and defined lines.

The paper brightness slider affects the color of the pencil. Move it to the right for the maximum color. Moving the slider to the middle produces a progressively gray pencil effect and to the left it goes black.

Above left: Pencil Width: 9, Stroke Pressure: 4, Paper Brightness: 0

Above right: Pencil Width: 2, Stroke Pressure: 13, Paper Brightness: 49

Right: Pencil Width: 2, Stroke Pressure: 4, Paper Brightness: 25, Difference filter 70%









DRY BRUSH

Paints edges using a dry brush technique that appears midway between an oil and watercolor effect. The range of colors is simplified as the filter looks at nearby pixels and blends them into areas of common color.

Brush Size: 9, Brush Detail: 9, Texture: 2



FILM GRAIN

Applies a pattern of grain that simulates real film. The higher you set the grain the more like fast film the effect becomes.

Grain: 8, Highlight Area: 13, Intensity: 1



CUTOUT

Builds up the image as though it's created by a collage of several pieces of torn colored paper. It has a similar look to a posterization effect. Number of levels: 6, Edge Simplicity: 3, Edge Fidelity: 1



FRESCO

Converts the image into a coarse stippled effect using short, rounded, quickly applied brush dabs. Good for a Classic painting effect. Brush Size: 2, Brush Detail: 6, Texture: 1, Fade filter by 59% and Darker blend mode.



NEON GLOW

Adds a glow to parts of the image. The glow color is selected by clicking the glow box and choosing a color from the color picker.

Size: 12, Brightness: 15, Color: Green, Fade filter 95% with Linear Light blend mode



ROUGH PASTELS

Makes an image appear as though it's on a textured background, covered in colored pastel chalk strokes. Stroke Length: 15, Stroke Detail: 8, Texture: Burlap, Scaling: 61%, Relief: 65, Light Direction: Right



PAINT DAUBS

A nice effect varied by altering the brush size to between 1 and 50, with a selected brush type that includes simple, light rough, light dark, wide sharp, wide blurry and sparkle.





PALETTE KNIFE

Similar to cutout, but with more blurred edges to emulate a palette knife style of painting. Will only suit certain images.

Stroke Size: 10, Stroke Detail: 2, Softness: 3



PLASTIC WRAP

Create Terminator style morphing by coating the image with a shiny plastic effect that accentuates surface detail. Highlight Strength: 13, Detail: 12, Smoothness: 7



SMUDGE STICK

Uses diagonal strokes to smudge or smear the darker areas and soften the image while lighter areas become brighter and lose detail. Stroke Length: 8, Highlight Area: 14, Intensity: 5



SPONGE

This is supposed to give an appearance of the image being painted with a sponge. Hmmm! Brush Size: 2, Definition: 1, Smoothness: 4



UNDERPAINTING

Makes the image appear with a textured background that shows through the surface. Brush Size: 9, Texture Coverage: 8, Texture: Canvas, Scaling: 98%, Relief: 24, Light Direction: Top right

OK

Cancel

▼ Preview



POSTER EDGES

Creates poster style effects by reducing the number of colors in the image and adding black lines around edges. Edge Thickness: 2, Edge Intensity: 7, Posterization: 0, No Fade 20% saturation.



WATERCOLOR

Saturates colors and paints in a watercolor style by simplifying image detail. Can become too contrasty if you're not careful. Brush Detail: 8, Shadow Intensity: 0, Texture: 2

● As with most filters and styles once the effect has been applied you can fade the result using the Edit → Fade command. Add a Blend mode to make the result very different than the original filter effect. Here's a couple of examples using the Artistic filters, but turn to the Fade page for more ways to use this excellent control.




Above Cutout and Plastic Wrap were applied in succession each using fade and a Blend mode. Right: Fresco faded followed by a duplicate layer with threshold command and Saturation blend, reduced to 70%. The key is experiment – you never know what will happen.

Assign Profile:

O Don't Color Manage This Document

O Working CMYK: Light GCR 340 UCR CMYK Euro Positi...

Profile: ColorMatch 3.01 - SWOP Ink, Sheetfed, Coated



Assign profile

MENU IMAGE →
MODE →
ASSIGN PROFILE

An option that lets

you select a color profile to your image so that it will always request being opened in this mode or will indicate that a different profile is being used.

Audio Annotation tool

If you have a microphone plugged into the audio-in point of your computer you can record short audio messages and place them on a picture. The annotation appears as a small speaker icon which, when clicked, will replay the recording. This is a great tool for designers who want to leave messages to the next person who will work on the image. It's also open to abuse!

(See Note)



Assign Profile



Auto Color correction

MENU	IMAGE →	An auto feature
	ADJUSTMENTS →	that first appeared
	AUTO COLOR	in version 7.0.
QUICK KE	YS CTRL+SHIFT+B	Clicking on the

Options button from the Curves dialogue box calls up a window that allows you to preset the way that each of the auto correction modes works.

Selecting Enhance Monochromatic Contrast clips all channels identically to ensure the photo holds its color values while making highlights appear lighter and shadows appear darker. Applying Auto Contrast from the Image Adjustments menu has the same effect.

Enhance Per Channel Contrast


maximizes the tonal range in each channel. This produces a more dramatic correction, but as each channel is adjusted individually a color cast may be removed or added. Applying Auto Levels uses this algorithm.

Find Dark & Light Colors locates the average lightest and darkest pixels and uses these to maximize contrast while minimizing clipping. This happens when the Auto Color command is used.

ilp

Add the same effect as placing a color filter over the front of your camera, by altering the color of the highlights or shadows. Below left: Here I selected maximum red from the color picker, which has produced a lith style effect. If you looked at the channels now you would see that the green and blue channel thumbnails were black.

Below right: Here's the result of a blue shadow selection and a green highlights. Don't forget to reset to white or any future auto adjustments will come out wrong.





Enhance Monochromatic Contrast

Clp: IETE %

Enhance Per Channel Contrast

Snap Neutral Midtones

Target Colors & Clipping

Highlights:

Save as defaults

Cancel



Auto Contrast

MENU	IMAGE →
	ADJUSTMENTS →
	AUTO CONTRAST

Auto mode that looks at the brightest and darkest parts

QUICK KEYS CTRL+ALT+SHIFT+L darkest parts of the image and adjusts the picture's highlights and shadows. It works well on some images, but it's often better to adjust the picture using Levels or Curves. (See Levels)





Auto Levels

MENU

IMAGE →
ADJUSTMENTS →

AUTO LEVELS

QUICK KEY CTRL+SHIFT+L

Scanned images using the auto setting rarely turn out with correct color or density so you need to adjust brightness and contrast.



Auto Levels looks for the brightest and darkest points and adjusts contrast so both maintain detail. It's a quick and easy fix, but learning how to adjust Levels manually produces better results. (See Levels)





Using any of the three Auto modes from the Image → Adjustments menu can provide a quick fix, but there are times when you have to choose the mode with care. The beauty with Photoshop is you can always undo an adjustment if you don't think it has worked well.

Here are two examples of when things can go wrong.

The first example (above left), of the couple on the steps, lacks contrast and has a slight warm color cast, so the obvious choice would be Auto Color, but this introduced a blue cast (above middle), Auto Contrast actually got it about right here (right).

The sunset picture (below) also looks a little dull, Auto Contrast did nothing, Auto Color did nothing and Auto Levels made a right mess of it (below middle). The only option here was to use Curves and adjust manually which has enriched the photograph (below right).







Automate


FILE → AUTOMATE A series of pre-written auto tasks used to make contact sheets, multi-format prints,

batch conversions and format pictures for your Web page.










Background color
Background eraser
Batch processing
Bevels
Bézier curves
Bicubic interpolation
Bitmap image
Bitmap mode
Blending modes
Blur filters
Borders
Brightness
Brushes
Burn tool

Background color

QUICK KEY X ALTERNATES
BETWEEN BACKGROUND
AND FOREGROUND COLOR

The default is white which appears in the lower box of the tools palette. You can change the color from white by clicking

on this box and using the color picker to select a new one. One reason for doing this is when making gradient fills which



progress from the foreground to background color. Erasing part of an image leaves the background color.

(See Foreground color)

Tip

To fill a selection with the Background color press Command+Delete.



Background eraser

A feature that first appeared on version 5.5 that makes it much easier to make selections. Now you paint over the area you want to remove using the Background

Fraser Tool E

Background Eraser Tool E

Magic Eraser Tool E

Eraser tool and the tool makes the

area transparent. Then when you copy and paste to a new layer it will look more natural.

Discontinguous erases the sample color wherever it appears in the picture; Contiguous erases pixels that are connected and Find Edges preserves edge sharpness.









Button mode